

BOXER™ Insecticide-Miticide

FIFRA SECTION 2(ee) RECOMMENDATION. This recommendation is made as permitted under FIFRA Section 2(ee) and has not been submitted to or approved by the EPA. **FOR USE AND DISTRIBUTION ONLY IN THE STATE OF TEXAS. Expiration Date 12/31/2026**

For systemic two-year control of listed pests in a variety of deciduous/coniferous ornamental trees and palm plants in utility rights-of-way, urban environments, residential areas and interior landscapes.

CONTAINS ADDITIONAL INFORMATION WHICH MAY NOT APPEAR ON PACKAGE LABEL. ALL APPLICABLE DIRECTIONS, RESTRICTIONS AND PRECAUTIONS ON THE PACKAGE LABEL ARE TO BE FOLLOWED.

This use permitted under FIFRA Section 2(ee)

EPA REG. NO. 69117-12

THIS RECOMMENDATION MUST BE IN THE POSSESSION OF THE USER AT THE TIME OF APPLICATION.

ALL DOSAGES MEASURED WITHIN 12" OF THE GROUND OR ROOT FLARE UNLESS OTHERWISE NOTED.

USE RATES

Tree Tissue	Target Pest	Application Rate Range	Comments
Shoot, Stem Trunk and Branch	Flatheaded Borers (such as adult and larvae of Emerald Ash Borer)	Inject 1-2 mls per 4" of trunk circumference measured within 12" of the ground	Injectations at the 1-2 ml rate will provide up to 2 years of control for Flatheaded Borers. Injectations may be made anytime translocation is occurring. Translocation typically ends within 6 weeks of the first frost. Consult your local extension office for timing.

HOW TO USE ARBORSYSTEMS CHEMICALS WITH ARBORSYSTEMS DIRECT-INJECT TREE INJECTION SYSTEM

1. Use only ArborSystems chemicals with your unit as they have been formulated specifically for the Direct-Inject system. Use of other chemicals will invalidate warranty.
2. Attach the chemical pack to the Direct-Inject unit and prepare the unit to make injections.
3. Set the delivery volume on the unit.
4. Follow the directions above to determine the amount of chemical and number of injection sites.
5. Determine where to make injections in the bark. Generally, the injection tip is inserted into the fissure (valley) of the tree bark. Inject thin-barked trees in the thicker part of the tree bark. Thick-barked trees require a longer injection tip.
6. Make injections working around the circumference of the tree. Make Wedgle® Tip injections within 12" of the ground. Portle® Tip injection height varies depending on type of tree and location.
7. When treating hardwoods, use Wedgle® Tips and make injections within 12" of the ground. Initially, use the shorter Wedgle Tip; if no resistance is met after this initial insertion past the bark (i.e., if the tip does not reach the outer xylem ring), withdraw the Tip. Replace the short Tip with the longer Tip to ensure the Tip fully penetrates the bark to reach the outer xylem ring. Use Portle® Tips when treating conifers and Palm Tips when treating palms.
8. When the Tip is correctly inserted, firmly squeeze the injection unit handles using a smooth, slow motion. This releases a pre-measured chemical dose into the tree.
9. Continue making injections moving around the tree until the entire tree trunk has been treated.
10. During use, periodically clean the Direct-Inject unit to prevent clogging.